

# Weedol® GUN! ROOTKILL PLUS™ WEEDKILLER

MAPP 14554

## WHY CHOOSE WEEDOL® GUN! ROOTKILL PLUS™?

- ✓ **SYSTEMIC** weedkiller, killing all garden broad-leaved and grass weeds down to the root so they won't grow back.
- ✓ **ACTS FAST**, with results visible in just 24 hours.

## INSTRUCTIONS FOR USE

### FOR USE ONLY AS A HOME GARDEN WEEDKILLER

For use on unwanted vegetation, areas not intended to bear vegetation and around garden plants.

### READ ALL SAFETY INSTRUCTIONS BEFORE USE

## WHEN TO USE

Use April - November, when weeds are actively growing.

J F M A M J J A S O N D

Use on a dry, calm day. Re-treat if rain falls within 6 hours of application.

## WHERE TO USE

Gravel areas, paths and drives, along fences, around sheds and greenhouses. Around the base of roses, ornamental shrubs, trees and under hedges (providing they are established, with woody bark). Take care to avoid drift! It's also ideal for ground clearance before autumn or spring digging and killing old lawns before reseeding or turfing.

## HOW TO USE

### SHAKE WELL BEFORE USE.

Always ensure the container is stored and carried upright when not spraying.

Mark out the area to be treated in metre squares.

1. Remove Power Sprayer from side clip. Unwrap plastic cover and dispose of safely. Unwrap hose completely. **Remove protective strip from battery compartment to activate batteries.**



2. Insert red hose connector at end of hose into red receptor in the bottle cap until it clicks. Raise the connector to vertical. This must remain up whilst spraying.



3. Flip open Power Sprayer until it locks into position. Twist nozzle at end of Power Sprayer to desired spray pattern. Select narrow spray setting for spot treatment of individual weeds or wide setting for larger areas.



4. Point Power Sprayer away from body. **Ensure grey trigger lock is disengaged before spraying.**



5. Point spray head 50 cm from surface to be treated. **Hold trigger for continuous spray.** Spray weeds thoroughly to the point of run-off, ensuring leaf surfaces and stem are covered evenly.



	Approx. number of seconds to treat 1 m <sup>2</sup>	Area treated by 5 L
Annual weeds	9 seconds	185 m <sup>2</sup>
Perennial weeds	10 seconds	170 m <sup>2</sup>
Brush weeds	12 seconds	145 m <sup>2</sup>

6. After Use: Push hose connector down and squeeze the trigger to clear nozzle. Take care to avoid clearing the nozzle over plants that you want to keep. Twist nozzle to OFF position and engage trigger lock. Flip the wand closed and store on the side clip without disconnecting the hose.

Visible effects in 24 hours. Weed death may take up to 28 days (in cold weather activity is slower).

### ONLY USE THE POWER SPRAYER WITH REFILLS OF THE PRODUCT ORIGINALLY PURCHASED Removing Power Sprayer from original bottle:

1. Remove the Power Sprayer by pulling the red hose connector from the red spout on cap.



### Attaching Power Sprayer to refill bottle:

3. Slide the side holder downward on the knob located at right-hand on the side of the refill container.



2. At the bottom of the Power Sprayer clip press the middle tab up and slide the holder upwards to remove it from the bottle.

4. Insert red hose connector into red spout on cap, until it clicks.

## TIP

**REPLANTING AND SOWING:** Treated area can be re-planted 7 days after spraying (to allow the weedkiller to move to the roots before cultivation).

## CAUTION

**Weedol® Gun! Rootkill Plus™** kills all green plant growth, including grass.  
**DO NOT APPLY TO LAWNS OR OTHER WANTED PLANTS UNLESS YOU WANT TO KILL THEM.**  
Direct spray away from ponds and other surface water bodies.

## SAFETY INSTRUCTIONS

### TO AVOID RISKS TO HUMAN HEALTH AND THE ENVIRONMENT, COMPLY WITH THE INSTRUCTIONS FOR USE.

#### Protection during / in use

Do not eat, drink or smoke when using this product.  
If medical advice is needed, have product container or label at hand.  
Keep off skin.  
Do not breathe spray.  
Wash hands and exposed skin after use.

#### Environmental protection

Harmful to aquatic life with long lasting effects.  
Use appropriate containment to avoid environmental contamination.  
Do not contaminate water with the product or its container.  
Do not empty into drains.

#### Storage and disposal

Keep out of reach of children.  
Keep away from food, drink and animal feeding stuffs.  
Keep product away from children and pets.  
**KEEP IN ORIGINAL CONTAINER**, tightly closed, in a safe place.  
**EMPTY CONTAINER COMPLETELY** and dispose of safely.

**Container:** Dispose of contents/container to a household waste recycling centre as hazardous waste except for empty containers which can be disposed of by recycling. Contact your local council for details.

**Power Sprayer:** Before disposing rinse the Sprayer through with water and dispose of at a local amenity recycling site.  
Contains 1, 2- Benzisothiazolin-3-one (BIT). May produce an allergic reaction.

### Replacing the batteries:

Open battery compartment at the bottom of Power Sprayer, remove the used batteries and dispose of safely. Replace with four new AA batteries in the correct position as marked inside the battery compartment. Securely close battery compartment door. Never mix alkaline, carbon-zinc or rechargeable batteries.

### PROTECT FROM FROST

Contains 7.2 g/L glyphosate and 0.02 g/L pyraflufen-ethyl as a ready to use suspension formulation.

For more information visit  
[www.weedol.co.uk](http://www.weedol.co.uk)  
or call +44 (0) 1276 401 300

©2015 Evergreen Garden Care UK Ltd,  
1 Archipelago, Lyon Way, Frimley,  
Surrey, GU16 7ER, UK.

**EU Importer**  
Evergreen Garden Care France SAS,  
4, Allée des Séquoias,  
69760 LIMONEST,  
FRANCE.